


READY, STEADY, COOK

Stay cool in the kitchen with this handy pot holder and coordinating oven glove –
Ali Burdon shows you how to sew the set







YOU WILL NEED

FOR THE POTHOLDER

- Main fabric: 40x45cm
- Contrast fabric: 35x35cm
- Cotton wadding: 25x45cm
- Insulated wadding: 25x45cm
- Matching thread
- Basic sewing kit

FOR THE OVEN GLOVE

- Main fabric: 42x33cm
- Contrast fabric: 40x40cm
- Cotton wadding: 44x35cm
- Insulated wadding: 44x35cm
- Iron-on interfacing: 31x39cm
- Matching thread
- Basic sewing kit

NOTES

- Download the template from gathered.how/ss-templates

POT HOLDER

CUTTING OUT

Step one Download the pot holder pocket template and cut it out.

Step two From the main fabric cut:

Back: 22x22cm

Pocket: two using the template.

Step three From the contrast fabric cut:

Back: 22x22cm

Pocket Binding: 4.5x20cm

Hanging Loop: 4x13cm

Pot Holder Binding: 4.5x35cm cut on the bias.

Step four From the cotton wadding cut:

Back: 25x25cm

Pocket: one using the template.

Step five From the insulating wadding cut:

Back: 25x25cm

Pocket: one using the template.

MAKING THE MAIN BODY

Step one Place the contrast fabric Back right sides (RS) down with insulating wadding Back on top, then the cotton wadding Back and main fabric. Back RS up on top.

Step two Pin the four layers together.

Step three Quilt together in your desired pattern. We quilted a crosshatch design, starting with central crossing lines. **01**

Step four Cut the quilted piece into a 20cm diameter circle. You can use a plate or other round

object for this. Alternatively you can create a template by folding a piece of paper into quarters and then tying a piece of string to a pencil. Measure 10cm along the string and hold this point at the centre of the folded paper. Use the string to move around the point, drawing the circle.

ADDING THE POCKET

Step one Press the Pocket Binding in half lengthways with wrong sides (WS) together and press. Open then fold the long edges to meet in the centre. Press then fold in half lengthways and topstitch together down both long edges. **02**

Step two With the two main fabric Pocket pieces RS out, sandwich the wadding in between.

Step three Pin the Pocket Binding to the top edge of the Pocket RS together, aligning raw edges. **03**


Step four Sew, then trim the excess. Fold the Pocket Binding over and slipstitch in place.

Step five Place the Pocket on top of the quilted piece with the insulated wadding facing RS out and matching the lower circle edges. Tack the pocket in place, just in from the edge.

ATTACHING THE HANGING LOOP

Step one Turn under and press the long edges of the Hanging Loop strip in the same way as for the Pocket Binding strip then topstitch together down both long edges.

Step two Fold in half and pin the short ends to the top of the pot holder. **04**



BINDING THE EDGES

Step one Join the Pot Holder Binding strips as shown, lining up the short edges and keeping the bias of the fabric in the same direction. ⁰⁵

Step two Trim this to 64cm, then turn under and press in the same way as the Pocket Binding strip.

Step three Open out the Pot Holder Binding strip at one short end and fold it under by 1cm.

Step four Starting with this end and working on the pocket side, pin the first 10cm of binding to the pocket with RS together, aligning raw edges and curving it round as you go. ⁰⁶

Step five Stitch in place, then continue around the pot holder in the same way.

Step six When you reach the start, overlap the folded end and continue for 2cm.

Step seven Trim the excess then fold the binding to the other side of the pocket, turning the other long edge under. Slipstitch in place.

Step eight Fold the Hanging Loop up and slipstitch the bottom of the loop to the binding to hold it in place.

OVEN GLOVE

CUTTING OUT

Step one Download the oven glove template and cut it out along the outer lines. Trace over the inner dotted stitching line and cut this out to make a separate stitching template.

Step two From the contrast fabric cut:

Hanging Loop: 4x11cm

Binding Strip: 4.5x36cm

Lining: 31x39cm.

MAKING THE OUTERS

Step one Place the insulated wadding on top of the cotton wadding then the main fabric right sides (RS) up on top and pin together.

Step two Quilt the three layers together by stitching diagonal lines spaced 4cm apart. Work the first line through the centre then stitch the lines outwards from here.

Step three Draw around the oven glove template on the quilted fabric. Flip over and draw around it again to make a pair and cut them out. ⁰⁷

Step four Place the stitching template on top of the cotton wadding side of one of the cut shapes and draw around it for your stitching line. ⁰⁸

ADDING A HANGING LOOP

Step one Press the Hanging Loop strip in half lengthways with wrong sides (WS) together and press. Open then fold the long edges to meet in the centre. Press then fold in half lengthways and topstitch together down both long edges.

Step two Fold in half to create a loop, then tack the short ends 4cm up from the bottom corner on the RS of one glove piece. ⁰⁹

Step three Pin the two sides of the glove RS together. Sew along the marked line. Trim seam allowance to 5mm and cut notches all around.

MAKING THE LINING

Step one Press interfacing to the WS of the Lining fabric following the manufacturer's instructions.

Step two Cut the two Lining pieces, flipping the template to cut a pair as before.

Step three Use the stitching template to mark the stitching line on the WS of one piece, then sew with RS together.

Step four Trim and notch the seam allowance. ¹⁰

BINDING THE EDGE

Step one Put the outer glove inside the Lining so they are WS together.

Step two Fold and press the Binding Strip in the same way as for the Hanging Loop.

Step three Fold one short end under 1cm.

Step four Pin the binding to the glove opening with RS together and matching raw edges. ¹¹

Step five Sew together, overlapping the short ends, then trim the excess. ¹²

Step six Fold the binding around the edge and slipstitch in place.

Step seven Turn the glove RS out to finish.




Designer, maker and craft blogger Ali Burdon specialises in patchwork and crochet. Find her crafty and gardening adventures on Instagram @msaliburdon

OVEN GLOVE

PAGE 70

ACTUAL SIZE


OVEN GLOVE



POT HOLDER

PAGE 70

ACTUAL SIZE



↖
*All templates are
available to download
from our website. Scan
the code to go straight to
the templates page!*

Thank you for making these projects from *Simply Sewing*. The copyright for these templates belongs to the designer of the project. They work hard to create projects for you to enjoy, so please don't re-sell or distribute their work without permission. Please do not make any part of the templates or instructions available to others through your website or a third party, or copy it multiple times without our permission. Copyright law protects creative work and unauthorised copying is illegal. We appreciate your help.